



Address: 24 Luna Close Swindon Wiltshire SN25 2LZ UK
Phone: +44 (0) 7792951549
Email: info@holbi.co.uk
Internet: http://www.holbi.co.uk

User's Manual

Project name: TrueLoaded

Module: Configuration

Logging

Project Leader: Vladislav Malyshev

QA: Eduard Shutenko

Technical Writer: Yana Lovyagina

version 1.2

o s C o m m e r c e m o d u l e s
I n t e g r a t i o n w i t h E R P s y s t e m s
S e r v i c e s
S k i n s

Table of Contents

Introduction.....	3
Store Page Parse Time.....	3
Log Destination.....	4
Log Date Format.....	4
Display The Page Parse Time.....	5
Store Database Queries.....	5

Introduction


From Admin Panel > Configuration > Logging section you can configure your logging settings to use in your web-store.

Store Page Parse Time


1. Go to the Admin Panel and click the **Configuration** link.



2. Select the **Logging** item.



3. Since the **Store Page Parse Time** item is highlighted, click the **Edit** button on the right.




- Select the **True** button to store the time spent on page parsing. The parse time will be displayed in the special log file which is specified in the Log Destination field (see below).
- Select the **False** button if you do not want to activate this feature.

- Click in the **Update** button.

Log Destination

- From the Admin Panel click the **Configuration** link and select the **Logging** item.
- Select the **Log Destination** item in the list and click the **Edit** button.




Title	Value	Action
Store Page Parse Time	false	
Log Destination	/var/www/html/turbo/images/page_parse_time.log	
Log Date Format	%d/%m/%Y %H:%M:%S	
Display The Page Parse Time	false	
Store Database Queries	false	
Store Page Parse to special IP-address	*	

- In the field, there are directory and name of the log file containing the page parse time: /tmp/page_parse_time.log. The log file is automatically created by the system in the **tmp** folder on your server.
- Click the **Update** button.

Log Date Format

- From the Admin Panel click the **Configuration** link and select the **Logging** item.
- Select the **Log Date Format** item in the list and click the **Edit** button.



Store Page Parse Time	false	
Log Destination	/var/www/html/turbo/images/page_parse_time.log	
Log Date Format	%d/%m/%Y %H:%M:%S	
Display The Page Parse Time	false	
Store Database Queries	false	
Store Page Parse to special IP-address	*	

- In the field, there is a date format for logging on the web-site. For example, the default format is “%d/%m/%Y %H:%M:%S”. In the log file it will look like this: dd/mm/YY, HH:MM:SS. For example, 01/01/07, 12:10:05
- Click the **Update** button.

Display The Page Parse Time

1. From the Admin Panel click the **Configuration** link and select the **Logging** item.
2. Select the **Display The Page Parse Time** item in the list and click the **Edit** button.




Title	Value	Action
Store Page Parse Time	false	
Log Destination	/var/www/html/turbo/images/page_parse_time.log	
Log Date Format	%d/%m/%Y %H:%M:%S	
Display The Page Parse Time	false	
Store Database Queries	false	
Store Page Parse to special IP-address	*	

- Select the **True** button to display the Page Parse Time. The parse time will be displayed at the bottom of the page after executing any actions on the web-site, e.g. after clicking the links. *Note: The Store Page Parse Time feature must be enabled.*
 - Select the **False** button if you do not want to activate this feature.
3. Click the **Update** button.

Store Database Queries

1. From the Admin Panel click the **Configuration** link and select the **Logging** item.
2. Select the **Store Database Queries** item in the list and click the **Edit** button.



Title	Value	Action
Store Page Parse Time	false	
Log Destination	/var/www/html/turbo/images/page_parse_time.log	
Log Date Format	%d/%m/%Y %H:%M:%S	
Display The Page Parse Time	false	
Store Database Queries	false	
Store Page Parse to special IP-address	*	

- Select the **True** button to store the database queries in the **page_parse_time.log** file. *Note: To enable this feature, your server version must be compatible with the PHP4.*
 - Select the **False** button if you do not want to activate this feature.
3. Click the **Update** button.