



Address: 24 Luna Close Swindon Wiltshire SN25 2LZ UK
Phone: +44 (0) 7792951549
Email: info@holbi.co.uk
Internet: http://www.holbi.co.uk

User's Manual

Project name: TrueLoaded

Module: Configuration

Links

Project Leader: Vladislav Malyshev

QA: Eduard Shutenko

Technical Writer: Yana Lovyagina

version 1.2

o s C o m m e r c e m o d u l e s
I n t e g r a t i o n w i t h E R P s y s t e m s
S e r v i c e s
S k i n s

Table of Contents

Introduction	3
Updating Click Count.....	3
Updating Spider Friendly Links.....	4
Updating Links Image Width.....	5
Updating Links Image Height.....	5
Updating Display Link Image.....	6
Updating Display Link URL.....	7
Updating Display Link Title.....	8
Updating Display Link Description	9
Updating Display Link Click Count	9
Updating Link Title Minimum Length.....	10
Updating Link URL Minimum Length.....	11
Updating Link Description Minimum Length.....	11
Updating Link Contact Name Minimum Length.....	12
Updating Link Check Phrase	12

Introduction

From the Admin Panel > Configuration > Links section you can set up configuration of links used in your web-store for Links Exchange program.

Updating Click Count

1. From the Admin Panel click the **Configuration** link and select the **Links** item.



2. Since the **Click Count** item is highlighted, click the **Edit** button on the right.



- Select the **True** button to activate counting of link clicks. The statistic information about how many times the links were clicked can be viewed on the Links Info page.

Note: To open the Links Info page, scroll down the Home page and click the link in the **Our Links** box.

On the Front End:



If True, the clicks will be counted and displayed in the **Clicks** column:

LINKS			
Displaying 1 to 1 (of 1 links)			
Title+	Description	URL	Clicks
<input type="checkbox"/> BBC	BBC news site alive	http://bbc.com	4
Displaying 1 to 1 (of 1 links)			

- Select the **False** button if you do not want to activate this feature.
- 3. Click the **Update** button.

Updating Spider Friendly Links

1. From the Admin Panel click the **Configuration** link and select the **Links** item.
2. Select the **Spider Friendly Links** item in the list and click the **Edit** button.



- Select the **True** button to enable spider friendly links (recommended). This feature optimizes the links displayed on your website (on the Links Info page) for Internet Search Engines. (See the “**Links Manager_Links**” manual for additional information on how to create links).
 - Select the **False** button if you do not want to activate this feature.
3. Click the **Update** button.

Updating Links Image Width

1. From the Admin Panel click the **Configuration** link and select the **Links** item.
2. Select the **Links Image Width** item in the list and click the **Edit** button.




Title	Value	Action	Links Image Width
Click Count	True		
Spider Friendly Links	True		
Links Image Width	120		edit
Links Image Height	60		Maximum width of the links image.
Display Link Image	1		

3. In the field, specify the maximum width of the link's image.
4. Click the **Update** button.

Updating Links Image Height

1. From the Admin Panel click the **Configuration** link and select the **Links** item.
2. Select the **Links Image Height** item in the list and click the **Edit** button.




Title	Value	Action	Links Image Height
Click Count	True		
Spider Friendly Links	True		
Links Image Width	120		
Links Image Height	60		edit
Display Link Image	1		Maximum height of the links image.

3. Update link image height the same way as it is described in steps 2-3 for Links Image Width.

Updating Display Link Image

1. From the Admin Panel click the **Configuration** link and select the **Links** item.
2. Select the **Display Link Image** item in the list and click the **Edit** button.



3. Here you can specify the location of the link's image on the Links Info page.
 - To display the image in the leftmost position, specify 1 in the field.



- To display the image to the left of Description, specify 2 in the field.



- To display the image to the left of URL, specify 3 in the field.








- To display the image in the rightmost position, specify any number greater than 4 in the field (e.g. 5, 6, 7, etc.).

Displaying 1 to 1 (of 1 links)				Result Pages: 1
Title+	Description	URL	Clicks	
BBC	BBC news site alive	http://bbc.com	4	
Displaying 1 to 1 (of 1 links)				Result Pages: 1

- Specify 0 in the field to hide the link's image.
- Click the **Update** button. (See the “**Links Manager_Links**” manual for additional information on how to add Link Image.)

Updating Display Link URL


- From the Admin Panel click the **Configuration** link and select the **Links** item.
- Select the **Display Link URL** item in the list and click the **Edit** button.

Configuration				osCommerce Catalog Admin Log
:: Links				
Title	Value	Action	Display Link URL	
Click Count	True		<input type="button" value="edit"/>	
Spider Friendly Links	True			
Links Image Width	120			
Links Image Height	60			
Display Link Image	5			Do you want display the L URL?
Display Link URL	4			Date Added: 10/29/2004
Display Link Title	2			

- Here you can specify the location of the link's URL on the Links Info page:
 - To display URL in the leftmost position, specify 1 in the field.
 - To display URL next to the link's image, specify 2 in the field, etc.
 - To display URL in the rightmost position, specify any number greater than 5 in the field (e.g. 6, 7, 8, etc.).
 - Specify 0 in the field to hide the link's URL.
- Click the **Update** button.

Updating Display Link Title

1. From the Admin Panel click the **Configuration** link and select the **Links** item.
2. Select the **Display Link Title** item in the list and click the **Edit** button.



Title	Value	Action	Display Link Title
Click Count	True		<input type="button" value="edit"/>
Spider Friendly Links	True		
Links Image Width	120		
Links Image Height	60		
Display Link Image	1		Do you want to display the Link Title?
Display Link URL	4		Date Added: 10/29/2004
Display Link Title	2		
Display Link Description	3		

Here you can specify the location of the link's title on the Links Info page the same way as it is described for Link Image and Link URL.

- In the field, specify any number from 1 - 5 to specify **Title's** location on the Links Info page. For example, specify 2 to display the link's **Title** next to the link's image.



LINKS				
Displaying 1 to 1 (of 1 links)				Result Pages: 1
	Title+	Description	URL	Clicks
	BBC	BBC news site alive	http://bbc.com	4

- Specify 3 in the field to display link's **Title** next to the Description, etc.
- Specify 0 in the field to hide the link's title.

3. Click the **Update** button.

Updating Display Link Description

1. From the Admin Panel click the **Configuration** link and select the **Links** item.
2. Select the **Display Link Description** item in the list and click the **Edit** button.

Title	Value	Action	Display Link Description
Click Count	True		<input type="button" value="edit"/> <p>Do you want to display the Link Description?</p> <p>Date Added: 10/29/2004</p>
Spider Friendly Links	True		
Links Image Width	120		
Links Image Height	60		
Display Link Image	1		
Display Link URL	4		
Display Link Title	2		
Display Link Description	3		
Display Link Click Count	5		
Link Title Minimum Length	2		


3. In the field, put appropriate number to specify the location of the link's **Description** on the Link Info page. Specify the Description location the same way as it is described for Link Image, Link URL, and Link Title.
 - Specify *0* in the field to hide the link's **Description**.
4. Click the **Update** button.

Updating Display Link Click Count

1. From the Admin Panel click the **Configuration** link and select the **Links** item.
2. Select the **Display Link Click Count** item in the list and click the **Edit** button.

Display Link Title	2	
Display Link Description	3	
Display Link Click Count	5	
Link Title Minimum Length	2	
Link URL Minimum Length	10	
Link Description Minimum Length	10	

- In the field, put a number to specify location of the **Clicks** (the Link Click Count statistics) on the Link Info page. Specify the Clicks location the same way as it is described for the Link Image, Link URL, and Link Title. For example, specify *1* in the field to display **Clicks** in the leftmost position.



- Specify 0 in the field to hide the **Clicks**.
- Click the **Update** button.

Updating Link Title Minimum Length

- From the Admin Panel click the **Configuration** link and select the **Links** item.
- Select the **Link Title Minimum Length** item in the list and click the **Edit** button.

Title	Value	Action	Link Title Minimum Length
Click Count	True		<div style="text-align: right;">  Minimum length of link title. Date Added: 10/29/2004 </div>
Spider Friendly Links	True		
Links Image Width	120		
Links Image Height	60		
Display Link Image	1		
Display Link URL	4		
Display Link Title	2		
Display Link Description	3		
Display Link Click Count	1		
Link Title Minimum Length	2		
Link URL Minimum Length	10		
Link Description Minimum Length	10		

- In the field, specify the minimum amount of characters to use in Link Title.
- Click the **Update** button.

Updating Link URL Minimum Length

1. From the Admin Panel click the **Configuration** link and select the **Links** item.
2. Select the **Link URL Minimum Length** item in the list and click the **Edit** button.

Title	Value	Action	Link URL Minimum Length
Click Count	True	ⓘ	<input type="text" value="10"/> edit Minimum length of link URL. Date Added: 10/29/2004
Spider Friendly Links	True	ⓘ	
Links Image Width	120	ⓘ	
Links Image Height	60	ⓘ	
Display Link Image	1	ⓘ	
Display Link URL	4	ⓘ	
Display Link Title	2	ⓘ	
Display Link Description	3	ⓘ	
Display Link Click Count	1	ⓘ	
Link Title Minimum Length	2	ⓘ	
Link URL Minimum Length	10	▶	
Link Description Minimum Length	10	ⓘ	

3. In the field, specify the minimum amount of characters to use in the Link URL.
4. Click the **Update** button.

Updating Link Description Minimum Length


1. From the Admin Panel click the **Configuration** link and select the **Links** item.
2. Select the **Link Description Minimum Length** item in the list and click the **Edit** button.

Display Link Description	3	ⓘ
Display Link Click Count	1	ⓘ
Link Title Minimum Length	2	ⓘ
Link URL Minimum Length	10	ⓘ
Link Description Minimum Length	10	▶
Link Contact Name Minimum Length	2	ⓘ
Links Check Phrase	yahoo linux	ⓘ

3. In the field, specify the minimum amount of characters to use in the Link Description.
4. Click the **Update** button.

Updating Link Contact Name Minimum Length


1. From the Admin Panel click the **Configuration** link and select the **Links** item.
2. Select the **Link Contact Name Minimum Length** item in the list and click the **Edit** button.



3. In the field, specify the minimum amount of characters to use in the Link Contact Name.
4. Click the **Update** button.

Updating Link Check Phrase

1. From the Admin Panel click the **Configuration** link and select the **Links** item.
2. Select the **Link Check Phrase** item in the list and click the **Edit** button.



3. In the field, specify a phrase to look for when you perform a link check. The Link Check is performed in the Links Manager. (See the “**Link Manager_Links**” manual for additional information about Link Check)
4. Click the **Update** button.