



Address: 24 Luna Close Swindon Wiltshire SN25 2LZ
Phone: +44 (0) 7792951549
Email: info@holbi.co.uk
Internet: http://www.holbi.co.uk

User's Manual

Project name: TrueLoaded

**Module: Design
Controls_Template Admin**

Project Leader: Vladislav Malyshev

QA: Eduard Shutenko

Technical Writer: Yana Lovyagina

version 1.2


o s C o m m e r c e m o d u l e s
I n t e g r a t i o n w i t h E R P s y s t e m s
S e r v i c e s
S k i n s

Table of Contents

Introduction.....	3
Template Admin	3
Table Cellpadding	4
Left Column.....	5
Right column.....	5
Select Modules for Mainpage	6
Other	6

Introduction


From the Admin Panel click the **Design Controls** link. This section allows for management of the web-shop design.



Template Admin


This page allows for setting of parameters responsible for web-shop design. A customer can order a web-store with one or few variants of design styles.

If you have purchased the web-store provided with a few design variants, you should select a necessary Template (design variant) first, and then activate it by clicking the **Active** icon (green traffic light).




You can also specify what columns should be displayed on the web-store pages. To do that, do the following:

1. To display the left column on the web-store frontend, click the “Y” icon in the **Display Left Column?** column. To hide the left column, click the “N” icon accordingly.



- To display the right column on the web-store frontend, click the “Y” icon in the **Display Right Column?** column. To hide the right column, click the “N” icon.



- To open detailed editing mode of the website design style, click the **Edit** button on the right.



- First, set the web-store page width. This parameter is set by percentage value, e.g. 100% is the full-screen width. Accordingly, 50% is a half-screen width (*Note: The template's display is aligned in the midst*). If there is a value 100%, the template's display will not be wider than a screen, since the number greater than 100 is approximated to 100% automatically. The same thing happens with the value less than 50 - the system approximates such value to 50%.

Edit Template

Please make any necessary changes

Template Name: Original

Site Width

Table Cellpadding

Here you can specify the number of pixels between the middle column and the right/left columns on the frontend.

- The **Main Table Cellpadding** field allows for specifying the number of pixels to widen/narrow the middle column (the values are 0-10). Default value is 0.
- The **Sub Table Cellpadding** field allows for specifying the number of pixels to widen/narrow the left and right columns (the values are 0-10). Default value is 10.

If you specify “0” in both fields, the space between the central and side columns will be minimal and the columns will be displayed too close to each other, if you specify “10” in both fields, the - space will be maximum.

Table cellpadding

Main table cellpadding

Sub table cellpadding

Left Column


- To display the left column in the web-store frontend, select the **Yes** radio button under **Include the left column?**

Left column

Include the left column?
 yes no

Set the left column width

Left column cellpadding




- In the **Set the left column width** field, specify the number of pixels for the left column width. Default value is 200.

Left column

Include the left column?
 yes no

Set the left column width

Left column cellpadding




- The minimum size of the left column is 140 pixels, so the numbers less than 140 specified here are considered as “140”.
 - The maximum width of the column is unlimited, but if you specify here the value greater than 400, the horizontal scrollbar appears, that's why it's strongly recommended to not make the left column too wide, except the urgent cases .
- Left Column Cellpadding** parameter defines a height of the left column boxes displayed vertically. 0 – the boxes are too close to each other, 10 – the space between boxes is maximum.

Right column

Set up the right column parameters the same way as it is described for the left column above:

- Select the **Yes** button to display the right column on the frontend.
- Specify the right column width and height.


- Specify parameter of the right column boxes height in the **Right Column Cellpadding** section. 0 – the boxes are too close to each other, 10 – the space between boxes is maximized.



Right column
Include the right column?
yes no
Set the right column width
Right column cellpadding

Select Modules for Mainpage

Here you can specify modules, which will form the main page of your web-store.




Select Modules for Mainpage

-
-
-
-
-
-

Warning! Please be careful while using this option – it's applied by developers. If the modules are set up incorrectly, the web-store will work incorrectly or crash!

Other

Here you can specify **Customer Greeting** parameter. You can either greet a customer visiting your web-store or not.



Other
Show customer greeting?
yes no
Include main table border
yes no
Show Mainpage Headers?
yes no

If you select the **Yes** button under **Show customer greeting?**, the **“Welcome Guest”** greeting will show up on the screen, accordingly, if you select the **No** button – the greeting won't show up.

